Pyro S Firmware Update Manual

Pyro S release note

| Release date | Firmware version | Updates | Firmware download |
|--------------|---------------------------------|---|-------------------|
| 20240419 | Pyro_S_H100_V1.0.1.6 | Initial version | <u>Download</u> |
| 20240712 | Pyro_S-V1.0.1.6_Interim Version | Interim Version If the verion is below 1.0.2.0, please update this version first | <u>Download</u> |
| 20240712 | Pyro_S_H100_allversion_V1.0.3.2 | Fixed known issues If the version is above 1.0.2.0, then you could upgarde directly, else you need upgrade Interim version firstly | <u>Download</u> |
| 20241015 | Pyro_S_H100_V1.0.3.9 | Fixed known issues Release for version above V1.0.3.2,if the version is below 1.0.3.9,please update 1.0.3.2 first. | <u>Download</u> |
| 20250410 | Pyro_S_H100_V1.0.4.2 | Release for H100 version. Optimizing performance Unicast mode support 1TX & 4RX | <u>Download</u> |
| 20250410 | Pyro_S_H110_V1.0.4.2 | Release for H110 version. Optimizing performance Unicast mode support 1TX & 4RX | <u>Download</u> |

Attentions


- Make sure the device have enough power when updating, pls don't unplug the USB disk before the update process is completed and successful.
- The device will change to default settings automatically after updated.
- The firmware updating takes the risks to cause unknown error, pls do not upgrade the device when you using it on-site.

How to check the device's firmware version

Long press the middle button to enter the menu page, select the system---version info to check the firmware version.

Operations to update the Pyro S firmware version

1. Prepare a USB flash disk with Type-C connector and storage less than 32GB, format the USB disk to FAT32.



- 2. Download the firmware to USB flash disk and make sure it is under the root directory, pls don't put it inside of any folder.
- 3. Connect the USB disk to Pyro S via type-C port, it will recognize the USB disk automatically and start to updating

If update failed after tried several times, you can contact our technical support team from Hollyland for help: support@hollyland.com