Pyro S Firmware Update Manual

Pyro S release note

Release date	Firmware version	Updates	Firmware download
20240419	Pyro_S_H100_V1.0.1.6	Initial version	Download
20240712	Pyro_S-V1.0.1.6_Interim Version	Interim Version If the verion is below 1.0.2.0, please update this version first	Download
20240712	Pyro_S_H100_allversion_V1. 0.3.2	Fixed known issues If the version is above 1.0.2.0, then you could upgarde directly, else you need upgrade Interim version firstly	<u>Download</u>
20241015	Pyro_S_H100_V1.0.3.9	Fixed known issues Release for version above V1.0.3.2, if the version is below 1.0.3.9, please update 1.0.3.2 first.	<u>Download</u>

Attentions

- Make sure the device have enough power when updating, pls don't unplug the USB disk before the update process is completed and successful.
- The device will change to default settings automatically after updated.
- The firmware updating takes the risks to cause unknown error, pls do not upgrade the device when you using it on-site.

How to check the device's firmware version

Long press the middle button to enter the menu page, select the system---version info to check the firmware version.

Operations to update the Pyro H firmware version

1. Prepare a USB flash disk with Type-C connector and storage less than 32GB, format the USB disk to FAT32.

Format USB Drive (F:) \times	USB Drive (F:) Properties	\times
Capacity: 7.49 GB ~	General Tools Hardware Sharing Customize	
File system FAT32 (Default) ~		
Allocation unit size 4096 bytes ~	Type: USB Drive	_
Restore device defaults	File system: FAT32 Used space: 17,534,976 bytes 16.7 MB	_
Volume label	Free space: 8,018,722,816 bytes 7.46 GB	
Format options	Capacity: 8,036,257,792 bytes 7.48 GB	_
Start Close	Drive F:	

- 2. Download the firmware to USB flash disk and make sure it is under the root directory, pls don't put it inside of any folder.
- 3. Connect the USB disk to Pyro S via type-C port, it will recognize the USB disk automatically and start to updating

If update failed after tried several times, you can contact our technical support team from Hollyland for help: support@hollyland.com